



1. Take off <u>cover</u> and place negatives <u>shiny side down</u> in negative holder. Then place the cover back on.



2. Place negative holder in scanner bed, matching the "A" tab with the "A" on the scanner bed.



3. On your desktop, search for Epson Scan. *If you computer doesn't have it, Image Capture works too

4. This window will pop up. Make sure your settings match this example:

5. Click "Preview"

0 0 0	EPSON Scan
EPSON	Scon Mode:
LESUN	Scan Professional Mode
Settings	
Name:	Current Setting 🕄
	Save Delete
Original	
Document Type:	Film
Film Type:	B&W Negative Film
Destination	
Image Type:	16-bit Grayscale
Resolution:	1200 💼 dpi
Document Size:	
W 2.70	H 9.54 in.
Target Size:	Original 🗘
Adjustments	
🍳 🔟	🚏 😢 Reset
🕨 🗹 Unsharp Mask	
Grain Reduction	
Color Restoration	on
Backlight Correction	ction 🖌
	Ť
Preview	📑 Scan
	Quic
Help	Configuration

6.Now this preview window will pop up. To scan individual frames, click "Thumbnail"

0 0	EPSON Scan	
EPSON	Scan Professional Mode	
Settings		1
Name:	Current Setting	
	Save Delete	
Original		
Document Type:	Film	
Film Type:	B&W Negative Film	
Destination		
Image Type:	16-bit Grayscale	
Resolution:	1200 😧 dpi	
Document Size:		
W 2.70	H 9.54 in.	
Target Size:	Original 🔹 🔝	
Adjustments		
🌣 🔟	🚏 😥 Reset	
🕨 🗹 Unsharp Mask		
🕨 📃 Grain Reductio	n	
Color Restorat	ion	
Backlight Corre	ection	
	▼	
Preview	📑 Scan 🔯	

Qui

Preview Normal Thumbnail Frame Ê **L** All -1 🗹 2 ? ↔ 1.40in. **1** 0.89in. 1680 x 1068 pixels 3.42 MB

7. Select which frames you'd like to scan.
Then click "Scan" on the other window.